


ControlByWeb Cloud | Quick Start Guide

The ControlByWeb Cloud makes monitoring and controlling remote devices much easier. You can add as many I/O devices as you need by purchasing Device Seats, and each device can have various end points such as sensors, switches, or other ControlByWeb modules attached at no additional cost. You can use a few cloud compatible devices to connect many end points which provide centralized monitoring of vast networks of sensor.

This quick start guide shows you how to create a cloud account, how to add Device Seats, and how to add I/O devices. For additional information, visit: www.ControlByWeb.com/cloud/

I. Create an Account


- Go to: ControlByWeb.cloud
- Click 'Create Account' located below the login button.
- Enter a username, first and last name, email, company name [optional], and password.
- Click the Terms and Conditions link to read and agree.
- Click 'Create Account'.
- Check your inbox for an email verification and click on the 'Verify Email Address' link. This will redirect you to the login page.
- Log in with your username and password.




The 'New Account' form contains the following fields: Username, First Name, Last Name, Email, Company Name (optional), New Password, and Confirm New Password. Below the password fields is a link for 'Terms and Conditions'. At the bottom are two buttons: 'Create Account' (green) and 'Cancel' (grey).

2. How to Add Device Seats

- Purchase your device seats at ControlByWeb.com/cloud/
- Once purchased, an email will be sent with your 'Device Seat Code'. Write down or copy the code.
- Log into your cloud account at ControlByWeb.cloud
- Click on your name in the top-right corner of the browser window and select the 'Register Device Seat Codes' menu option.
- Type or paste the Device Seat Code into the form and click 'Submit'.
- You will be redirected to the Summary page where you can see that your device seat has been added.



Register Codes





The 'Register Codes' form includes a section for 'Add Device Seats' with the text 'Add Device Seats To Account: ControlByWeb'. It features a 'Device Seat Code' label and an input field with the placeholder 'Enter the Device Seat Code'. At the bottom are 'Submit' (green) and 'Cancel' (grey) buttons.

ControlByWeb Cloud | Quick Start Guide

3a. Add Ethernet/Wi-Fi Devices

- Log into your cloud account at ControlByWeb.cloud
- Click on 'Devices' in the left-hand navigation panel.
- Click the 'New Device +' button in the top-right corner of the 'Device List' table.
- On the New Device page, you have two tabs: Device or Cell Device.
- Ensure the 'Device' tab is highlighted blue.
- Click the 'Generate Token +' in the top-right corner of the table.
- A token will appear in the table. Highlight and copy the token.
- In a separate browser tab or window, visit the device's setup page by typing its IP address followed by `setup.html` [For more information on accessing your device's IP address and setup pages, see the device's quick start guide and/or users manual, available for download at: ControlByWeb.com/support]
- On the device's setup page, click 'General Settings' in the left-hand navigation panel to expand that section and select 'Advanced Network'.
- Enable Remote Services by clicking 'Yes' under the Remote Services section and ensure the Version drop-down selection is '2.0'.
- Under the Certificate Request Method drop-down, select 'Certificate Request Token' and paste the token you generated in the Certificate Request Token field.
- Click 'Submit' at the bottom of the page.
- Navigate back to your cloud account and select 'Devices' from the left-hand navigation panel.
- Your device will appear on the Devices page as long as your Internet connection is stable.
- You can now access the device's Control and Setup pages.



ControlByWeb Cloud | Quick Start Guide

3b. Add & Activate Cellular Devices

- Log into your cloud account at ControlByWeb.cloud
- Click on 'Devices' in the left-hand navigation panel.
- Click the 'New Device +' button in the top-right corner of the device table.
- On the New Device page, you have two tabs: Device or Cell Device.
- Ensure the 'Cell Device' tab is highlighted blue.
- Enter a device name. Enter the last 6 digits of the Serial Number and the full Cell ID found on the side of your ControlByWeb cellular device.
- Enter the data plan found in your purchase confirmation email. Activate the plan if required.
- Activation may take 15 minutes. Click 'Check SIM Status' or refer to the Summary page to verify activation status.
- Once activated, power on the cell device for the first time. It will connect to your cloud account automatically.
- You can now access the device's Control and Setup pages.

The image displays two screenshots of the ControlByWeb web interface. The left screenshot shows the 'Add Device' page with the 'Cell Device' tab selected. It contains fields for 'Cell Device Name', 'Serial Number' (with a dropdown for '00-0C-C8'), and 'Cell ID / ICCID'. A blue box provides instructions: 'Enter Cell ID (13 characters) or ICCID (18-22 characters) as appears on the device label.' There are 'Submit' and 'Cancel' buttons at the bottom. The right screenshot shows the 'Device Edit' page. It has a 'Cell Settings' section with a green 'SIM Activated' status. Below are fields for 'Cell ID' (containing '1000 122') and 'Data Plan Code'. A green 'Apply Data Plan Code' button is at the bottom.

More Cloud Features

There is more to the cloud than adding device seats and devices. This platform enables cloud-based data logging, parent-child account organization, quick access to on-device setup and control pages, and powerful user roles and sharing settings. For additional information, visit www.ControlByWeb.com/cloud